

Sedum (Autumn Stonecrop)

72ct Plug

Container:

Premium 1 Gallon Pot

Finish:

10-12 weeks

When To Plant:

Summer to late summer

Notes:

Bulk in summer for a full plant the following spring.

Grade #1 Bare Root

Container:

Premium 1 Gallon Pot

Finish:

8-10 weeks

When To Plant:

Spring to late spring

Growing Temperature:

70-75° F days

55-65° F nights.

Fertility:

Needs 100-200 ppm fertilizer for optimal growth.

Pests and Diseases:

Preventive fungicides recommended at time of transplant. Mildew can be problematic, treat as needed.

Moisture:

For potting soil use Professional planting media.

Avoid overwatering; extended periods of wet soil will be detrimental.

PGRs/Pinching:

One soft pinch, 1 week after planting. Second pinch optional. Florel® at 500ppm is also effective at increasing branching. B-9 / Cycocel tank mix will control growth; however, growing plants dry will also control growth. Larger plants with better branching and form will occur with vernalization.

Soil pH:

5.8-6.5

EC Level:

2.0-3.5 pour through method

Vernalization:

Not required.

Potting and Timing:

Some root trimming may be necessary at planting time to fit into the container.

Warm and slightly dry conditions after transplanting speeds rooting in and growth.

Planting Level:

Place crown just at or below soil level.

Lighting:

Requires high light in production; in a very high light environment, such as Southern California, plants may need up to 30% shade to protect against sun scorch.

Sedum require long days to flower. Once buds form plants can be moved to a short day environment.



WaltersGardens
INC

P.O. Box 137 • 1992 96th Ave. Zeeland, MI. 49464

Phone: 888-925-8377 • Fax: 800-752-1879

Email: sales@waltersgardens.com

www.WaltersGardens.com • www.PerennialResource.com

www.ProvenWinners.com